ECL Tool change notes 1.10.0.0 - 1.10.0.10 (2025 Q1) *Added support for updated and new applications *Removed check for update (user will manual check for new version on Danfoss webpage) 1.9.9.9 (20220317) *Update installer with new certificate 1.9.9.8 (20220112) *Added support for new applications and ECL versions *Added 'ECL Portal' and 'Leanheat Monitor' quick activation to connect page *Added initial support for P315 1.9.9.7 (20200812) *Added optinal test report field to print *Updated application and system xml files *Updated appliaction drawings 1.9.9.6 (20200214) *Updated application and system xml files 1.9.9.5 (20191111) *Fixed hanging update check *Fixed Graph state after reconnected device 1.9.9.4 (20181026) *Updated application and system xml files *Fixed print application drawing filtering 1.9.8.9 (20180524) *Updated ECL Tool version check sources *Updated application and system xml files *Fixed print function for specific A302 versions 1.9.8.8 (20171103) +Updated application lookup *Updated application and system xml files 1.9.8.6 (20160921) +Added Commandline options for start and connect to ECL from bat file, shortcut etc. *Updated application and system xml files 1.9.8.4 (20151130) *A Windows 10 update (build 1511) prevented the ECL Tool from starting up. This has been fixed so that the ECL Tool now works with the new Windows 10 version *Updated application and system xml files 1.9.8.3 (20151026)

*Now the correct unit is shown for raw sensor inputs S1-S19 including configurable inputs both in parameter overview and report *Expanded box for Production Mode Com port to show 2 digits *Made differentation on ECL model numbers. *Removed some unused settings from the parameter list if the ECL is an ECL 210 or ECL 296 *Changed print to xps to single column instead of double columns +Added possibility to copy a screenshot from the live ECL function to the Windows clip board by pressing CTRL+C +Added separate log screen with zoomable graph +Added option for including graphs in a report +Added possibility for reading an extended log with low time resolution from ECLs with firmware newer than 1.56 rev 8300 (2015-03-27) +Added buttons for adding a screenshot from Live ECL to the report when parameters have been loaded +Added translations to the Live ECL page +Fixed scale of configurable input so that current values are scaled according to current configuration type instead of always scaled by a factor of 100 1.9.7.37 (20150507) *Updated application and system xml files *Updated application drawings 1.9.7.36 (20140829) *Updated application and system xml files *Updated Serial PORT discovery 1.9.7.34(20140513)*Updated application and system xml files *Updated application example drawings *Removed editable Modbus address from Ethernet connection - alwas use ECL service address 254 1.9.7.32 (20140304) *Updated language (includes new languages) +Added advanced settings for easy change of ECL Portal name +Added MRU for IP Address (most recent used) 1.9.7.30 (20130827) *Updated application and system xml files *Updated application example drawings *Updated language +Added startup picture 1.9.7.28 (20130506) *Updated application and system xml files *Updated application example drawings *Minor change in print full mode (information about R/W and scale added) *Nederlands texts added

1.9.7.25(20121203)*Fixed slow COM Port selection *Updated ECL Tool Instruction 1.9.7.22 (20121112) *Added, "live ECL" save formats JPEG, Gif and Bitmap *Change, print format of limiter information *Fixed, print to xps or pdf printer. *Fixed, selection of serial COM ports 1.9.7.15(20120604)*Change, licenrance requirement for full features removed *Change, print format modified to reduce size and now includes page number *Change, print includes some translations 1.8.6.14 (20120329) +Added support for ECL 210/310 version 1.42 *Change, application drawings A2xx is now selectable for A3xx applications *Fixed Holiday write order (status written last) *Small UI changes (Scroll bar) 1.7.5.11 (20120221) +Added xml files *fixed Mouse drag Tool window 1.7.5.10 (20120217) +Added Application drawings, e.g. A217 *Fixed and changed log file sample order (now old -> new) *Fixed ECL 210 support 1.7.5.7 (20120206) +Demo mode added for non Danfoss PC (Write functions disabled) press the Demo label to request a license description box text selected on load -UI improvements -Print application drawing filenames change. The User add/remove files as needed *Fixed schedule default handling 1.7.5.1 (20120127) +Print layout refined +Improved handling of lost communication Demo function: +Print application drawing selectable (A266.1 and A237 - more will follow) +Heatcurve graphics 1.7.2 (20120112) +Log read improved